

Oracle® Database Vault

Installation Guide

10g Release 2 (10.2) for Microsoft Windows (32-Bit)

B32384-01

November 2006

Oracle Database Vault Installation Guide, 10g Release 2 (10.2) for Microsoft Windows (32-Bit)

B32384-01

Copyright © 2006, Oracle. All rights reserved.

Primary Author: Sumit Jeloka

Contributing Author: Pat Huey

Contributors: Scott Gaetjen, Xiaofang Wang, Jack Brinson, Chi Ching Chui, Kamal Tbeileh, Trivikrama Samudrala, Madhu Velukur, Mayur Mundada

The Programs (which include both the software and documentation) contain proprietary information; they are provided under a license agreement containing restrictions on use and disclosure and are also protected by copyright, patent, and other intellectual and industrial property laws. Reverse engineering, disassembly, or decompilation of the Programs, except to the extent required to obtain interoperability with other independently created software or as specified by law, is prohibited.

The information contained in this document is subject to change without notice. If you find any problems in the documentation, please report them to us in writing. This document is not warranted to be error-free. Except as may be expressly permitted in your license agreement for these Programs, no part of these Programs may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose.

If the Programs are delivered to the United States Government or anyone licensing or using the Programs on behalf of the United States Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the Programs, including documentation and technical data, shall be subject to the licensing restrictions set forth in the applicable Oracle license agreement, and, to the extent applicable, the additional rights set forth in FAR 52.227-19, Commercial Computer Software--Restricted Rights (June 1987). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

The Programs are not intended for use in any nuclear, aviation, mass transit, medical, or other inherently dangerous applications. It shall be the licensee's responsibility to take all appropriate fail-safe, backup, redundancy and other measures to ensure the safe use of such applications if the Programs are used for such purposes, and we disclaim liability for any damages caused by such use of the Programs.

Oracle, JD Edwards, PeopleSoft, and Siebel are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

The Programs may provide links to Web sites and access to content, products, and services from third parties. Oracle is not responsible for the availability of, or any content provided on, third-party Web sites. You bear all risks associated with the use of such content. If you choose to purchase any products or services from a third party, the relationship is directly between you and the third party. Oracle is not responsible for: (a) the quality of third-party products or services; or (b) fulfilling any of the terms of the agreement with the third party, including delivery of products or services and warranty obligations related to purchased products or services. Oracle is not responsible for any loss or damage of any sort that you may incur from dealing with any third party.

Contents

Preface	v
----------------------	---

Part I Oracle Database Vault Installation

1 Oracle Database Vault Installation Overview

Database Vault Installation Environment	1-1
Database Vault Accounts	1-1
Database Vault Owner	1-1
Database Vault Account Manager	1-2
Default Audit Policy and Initialization Parameters	1-2
Installation Considerations	1-2
Hardware and Software Certification	1-2
Multiple Oracle Homes	1-3

2 Installing Oracle Database Vault as an Option

Preinstallation and Installation Tasks	2-1
Become Familiar with the Features of Oracle Database Vault	2-2
Check the Hardware Requirements	2-2
Check the Software Requirements	2-3
Check the Database Requirements	2-4
Install Oracle Enterprise Manager Console DB	2-5
Apply Oracle Database Release 10.2.0.3 Patch Set	2-5
Prepare a Backup Strategy	2-6
Verify That Oracle Clusterware Is Running (RAC Only)	2-6
Stop Existing Oracle Processes	2-6
Stop the Enterprise Manager Database Control Process	2-7
Stop the iSQL*Plus Process	2-7
Shut Down All Database Instances	2-7
Stop Existing Listeners	2-7
Stop Oracle Services	2-7
Run Oracle Universal Installer to Install	2-8
Postinstallation Tasks	2-10
Back Up the Database	2-10
Change Passwords for Oracle-Supplied Accounts	2-10
Using SQL*Plus to Unlock Accounts and Reset Passwords	2-10

Enable or Disable Connections with the SYSDBA Privilege.....	2-11
Start the Listener and Database on Other Nodes (RAC Only).....	2-12
Run DVCA to Set Instance Parameters and Lock Out SYSDBA Sessions (RAC Only)	2-12
Restart Enterprise Manager Database Control	2-14
Removing Oracle Software.....	2-14

Part II Appendixes

A How to Stop Processes in an Existing Oracle Real Application Clusters Database

B Using Response Files

How Response Files Work.....	B-1
General Procedure for Using Response Files.....	B-2
Installing Database Vault Using a Response File	B-2
Prepare the Response File	B-2
Run Oracle Universal Installer Using the Response File.....	B-3
Troubleshooting Silent Mode Installation	B-4

C Running DVCA After Creating a Database Vault Database

D Database Listener Security Recommendations

Security Checklist for the Database Listener.....	D-1
---	-----

E Initialization Parameters

F Enabling Oracle Database Vault Administrator Accessibility

Enabling Oracle Database Vault Administrator Accessibility Mode	F-1
Providing Textual Descriptions of Database Vault Administrator Charts.....	F-2

Index

Preface

The Oracle Database Vault Installation Guide explains how to prepare for, install, and configure Oracle Database Vault with specific instructions for the operating system and Oracle software technology components that Database Vault requires.

Audience

This document is intended for Oracle DBAs as well as System Administrators who are involved in the installation of Oracle Database Vault and its related components.

Documentation Accessibility

Our goal is to make Oracle products, services, and supporting documentation accessible, with good usability, to the disabled community. To that end, our documentation includes features that make information available to users of assistive technology. This documentation is available in HTML format, and contains markup to facilitate access by the disabled community. Accessibility standards will continue to evolve over time, and Oracle is actively engaged with other market-leading technology vendors to address technical obstacles so that our documentation can be accessible to all of our customers. For more information, visit the Oracle Accessibility Program Web site at

<http://www.oracle.com/accessibility/>

Accessibility of Code Examples in Documentation

Screen readers may not always correctly read the code examples in this document. The conventions for writing code require that closing braces should appear on an otherwise empty line; however, some screen readers may not always read a line of text that consists solely of a bracket or brace.

Accessibility of Links to External Web Sites in Documentation

This documentation may contain links to Web sites of other companies or organizations that Oracle does not own or control. Oracle neither evaluates nor makes any representations regarding the accessibility of these Web sites.

TTY Access to Oracle Support Services

Oracle provides dedicated Text Telephone (TTY) access to Oracle Support Services within the United States of America 24 hours a day, seven days a week. For TTY support, call 800.446.2398.

Related Documents

For more information, refer to the following documents:

- *Oracle Database Vault Release Notes*
- *Oracle Database Vault Administrator's Guide*
- *Oracle Database Installation Guide for Microsoft Windows*
- *Oracle Database Oracle Real Application Clusters Installation Guide for Microsoft Windows*
- *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide*

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

Part I

Oracle Database Vault Installation

Part I introduces you to Oracle Database Vault installation concepts, requirements, and steps. This part contains the following chapters:

- [Chapter 1, "Oracle Database Vault Installation Overview"](#)
- [Chapter 2, "Installing Oracle Database Vault as an Option"](#)

Oracle Database Vault Installation Overview

Oracle Database Vault enables you to secure business data in ways that were not possible before. Database Vault uses a multifaceted and multilayered approach to implementing database security.

This chapter provides an overview of the Database Vault installation process. This chapter includes the following sections:

- [Database Vault Installation Environment](#)
- [Database Vault Accounts](#)
- [Installation Considerations](#)

Database Vault Installation Environment

Oracle Database Vault can be installed as an option to the following:

- Oracle Database 10g Release 2 (10.2.0.3) standalone installation
- Oracle Database 10g Release 2 (10.2.0.3) with Oracle Real Application Clusters (RAC)

Database Vault Accounts

Database Vault prompts for two accounts that you can create during installation. These are the Database Vault Owner and the Database Vault Account Manager accounts. You must supply an account name and password for the Database Vault Owner during installation. Creating a Database Vault Account Manager is optional.

Database Vault Owner

The Database Vault Owner account is granted the DV_OWNER role. This account can manage Database Vault roles and configuration.

The Database Vault Owner user name can be a minimum of 2, and a maximum of 30 characters long. The account password can be a minimum of 8, and a maximum of 30 characters.

The password that you choose for the Database Vault Owner account must be a secure one. The following password restrictions are enforced:

- The password must include at least one alphabet, one digit, and one nonalphanumeric character (symbol).
- The password cannot be the same as the account name.

- The password cannot contain any consecutive repeating characters.

Database Vault Account Manager

The Database Vault Account Manager is granted the `DV_ACCTMGR` role. This account is used to manage database user accounts. The Database Vault Account Manager is created to facilitate separation of duties. If you do not opt to create the Database Vault Account Manager account, then the `DV_ACCTMGR` role is granted to the Database Vault Owner account by default.

The Database Vault Account Manager user name can be a minimum of 2, and a maximum of 30 characters long. The account password can be a minimum of 8, and a maximum of 30 characters.

The same password restrictions that apply to Database Vault Owner are applicable to Database Vault Account Manager as well.

Default Audit Policy and Initialization Parameters

Oracle Database Vault installs a baseline database auditing policy. This policy covers the access control configuration information stored in Database Vault database tables, information stored in Oracle Catalog (rollback segments, tablespaces, and so on), the use of system privileges, and Oracle Label Security configuration.

See Also: *Oracle Database Vault Administrator's Guide* for more information on the database audit policy

When you install Oracle Database Vault, the security specific database initialization parameters are initialized with default values. These security specific initialization parameters are listed in [Appendix E](#)

Installation Considerations

This section contains information that you should consider before deciding how to install this product. It contains the following sections:

- [Hardware and Software Certification](#)
- [Multiple Oracle Homes](#)

Hardware and Software Certification

The platform-specific hardware and software requirements included in this installation guide were current at the time this guide was published. However, because new platforms and operating system software versions might be certified after this guide is published, review the certification matrix on the *OracleMetaLink* Web site for the most up-to-date list of certified hardware platforms and operating system versions. The *OracleMetaLink* Web site is available at the following URL:

<http://metalink.oracle.com>

If you do not have a current Oracle Support Services contract, then you can access the same information at the following Web site:

<http://www.oracle.com/technology/support/metalink/content.html>

Multiple Oracle Homes

This product supports multiple Oracle homes. This means that you can install this release or previous releases of the software more than once on the same system, in different Oracle home directories.

Installing Oracle Database Vault as an Option

This chapter includes an overview of the major steps required to install Oracle Database Vault into an existing Oracle Database 10g release 2 (10.2.0.3) database. These procedures transform an existing Oracle Database system (including associated applications) into an Oracle Database Vault system. Databases upgraded using the procedures described in this chapter can work almost in the same manner as in earlier releases and, optionally, can leverage new Oracle Database Vault functionality. For a list of changes that Database Vault makes, refer to [Appendix E, "Initialization Parameters"](#) and the *Oracle Database Vault Administrator's Guide*.

Note: In order to upgrade a pre-10g release 2 Oracle Database to Oracle Database Vault, you first need to upgrade the database to a 10g release 2 (10.2.0.3) database.

See Also: *Oracle Database Upgrade Guide, 10g Release2 (10.2)* for information about upgrading your Oracle Database to Oracle Database 10g release 2.

This chapter covers the following topics:

- [Preinstallation and Installation Tasks](#)
- [Postinstallation Tasks](#)
- [Removing Oracle Software](#)

Preinstallation and Installation Tasks

This section covers the following topics:

- [Become Familiar with the Features of Oracle Database Vault](#)
- [Check the Hardware Requirements](#)
- [Check the Software Requirements](#)
- [Check the Database Requirements](#)
- [Prepare a Backup Strategy](#)
- [Verify That Oracle Clusterware Is Running \(RAC Only\)](#)
- [Stop Existing Oracle Processes](#)
- [Run Oracle Universal Installer to Install](#)

Become Familiar with the Features of Oracle Database Vault

Before you plan the upgrade process, become familiar with the features of Oracle Database Vault. The *Oracle Database Vault Administrator's Guide* discusses the basic features of Oracle Database Vault.

Check the Hardware Requirements

Table 2–1 discusses the hardware requirements for Oracle Database Vault:

Table 2–1 Hardware Requirements

Requirement	Value
Physical memory (RAM)	256 MB minimum; 512 MB recommended
Virtual memory	Double the amount of RAM
Disk space	270 MB of disk space for the Oracle Database Vault software 400 MB of space in the temp directory 10 MB of additional disk space for the database files
Video adapter	256 colors
Processor	550 MHz minimum

To ensure that the system meets these requirements, follow these steps:

1. Determine the physical RAM size. For a computer using Windows 2003, for example, double-click **System** in the Windows Control Panel and click the **General** tab. If the size of the physical RAM installed in the system is less than the required size, then you must install more memory before continuing.
2. Determine the size of the configured virtual memory (also known as paging file size). For a computer using Windows 2003, for example, double-click **System** in the Control Panel, click the **Advanced** tab, and click **Settings** in the **Performance** section. Then click the **Advanced** tab. The virtual memory is listed in the **Virtual Memory** section.

If necessary, see your operating system documentation for information about how to configure additional virtual memory.

3. Determine the amount of free disk space on the system. For a computer using Windows 2003, for example, double-click **My Computer**, right-click the drive where the Oracle software is to be installed, and select **Properties**.
4. Determine the amount of disk space available in the temp directory. This is equivalent to the total amount of free disk space, minus what will be needed for the Oracle software to be installed.

If there is less than 400 MB of disk space available in the temp directory, then first delete all unnecessary files. If the temp disk space is still less than 400 MB, then set the TEMP or TMP environment variable to point to a different hard drive. For a computer using Windows 2003, for example, double-click **System** in the Control Panel, click the **Advanced** tab, and click **Environment Variables**.

Check the Software Requirements

Oracle Database Vault is installed in an existing Oracle home. All software requirements that were met while installing Oracle Database 10g release 2 are sufficient for Oracle Database Vault.

See Also: *Oracle Database Installation Guide for Microsoft Windows* for detailed information on the software requirements for installing Oracle Database

Table 2–2 lists the software requirements for Oracle Database Vault.

Table 2–2 Software Requirements

Requirement	Value
System Architecture	<p>Processor: Intel (x86), AMD64, and Intel EM64T</p> <p>The 32-bit Database Vault version, which this installation guide describes, runs on the 32-bit version of Windows on either x86 or x64 hardware. Oracle provides limited certification for 32-bit Oracle Database Vault on 64-bit Windows (x64). For additional information, visit <i>OracleMetaLink</i> at:</p> <p>http://metalink.oracle.com</p>
Operating System	<p>Oracle Database Vault for 32-bit Windows is supported on the following operating systems:</p> <ul style="list-style-type: none"> ■ Windows 2000 with Service Pack 1 or later. All editions, including Terminal Services and Microsoft Windows 2000 MultiLanguage Edition (MLE), are supported. ■ Windows Server 2003 - all editions. ■ Windows XP Professional - only standalone installation of Database Vault is supported <p>Windows NT is not supported.</p> <p>Windows Multilingual User Interface Pack is supported on Windows Server 2003 and Windows XP Professional.</p>
Compiler	<p>Pro*Cobol has been tested and certified with the following two compilers:</p> <ul style="list-style-type: none"> ■ ACUCOBOL-GT version 6.2 ■ Micro Focus Net Express 4.0 <p>Object Oriented COBOL (OOCOBOL) specifications are not supported.</p> <p>The following components are supported with the Microsoft Visual C++ .NET 2002 7.0 and Microsoft Visual C++ .NET 2003 7.1 compilers:</p> <ul style="list-style-type: none"> ■ Oracle C++ Call Interface ■ Oracle Call Interface ■ GNU Compiler Collection (GCC) ■ External callouts ■ PL/SQL native compilation ■ XDK

Table 2–2 (Cont.) Software Requirements

Requirement	Value
Network Protocol	<p>The Oracle Net foundation layer uses Oracle protocol support to communicate with the following industry-standard network protocols:</p> <ul style="list-style-type: none"> ■ TCP/IP ■ TCP/IP with SSL ■ Named Pipes
Oracle Database Client	<p>If you plan to connect to Oracle Database Vault from a release of Oracle Database Client that is earlier than 10g release 2 (10.2), you will not be able to do so if the following conditions exist:</p> <ul style="list-style-type: none"> ■ Oracle Database Client is running on the same computer as Oracle Database 10g Release 2 (10.2). ■ Microsoft Windows Terminal Services is not running on the same computer as Oracle Database Client. Typically, Terminal Services is installed and configured with Microsoft Windows 2003, but on Microsoft Windows 2000 or Windows XP, it may not be installed or enabled. ■ Oracle Database Client is version 8.0, 9.0–9.2.0.6, or 10.1–10.1.0.3. ■ Oracle Database Client is not running as Administrator. <p>To remedy this problem, upgrade Oracle Database Client by using the latest Oracle Database Family patchset (9.2.0.4, or 10.1.0.4 or later). You can download the patchset from the Patches and Updates section of <i>OracleMetaLink</i> at:</p> <p>http://metalink.oracle.com</p>

Check the Database Requirements

In order to install Oracle Database Vault, you must be running the Enterprise Edition of Oracle Database 10g release 2 (10.2.0.3). The database should also have Oracle Enterprise Manager Console DB 10.2.0.3.0 installed. In addition, the Database Vault installer requires write access to the files, `oratab` and `oraInst.loc`.

A listener must have been configured for the existing database. Oracle Net Configuration Assistant configures the listener when you first install the database. You can also use Oracle Enterprise Manager to administer listeners.

You must have an existing password file for the database. The password file authentication parameter, `REMOTE_LOGIN_PASSWORDFILE` must have been set to `EXCLUSIVE` or `SHARED`.

You can set the `REMOTE_LOGIN_PASSWORDFILE` parameter in the `init.ora` file. Use the `orapwd` utility to create and manage password files.

See Also: *Oracle Database Administrator's Guide* for more information on creating and maintaining a password file

The following topics discuss applying the 10.2.0.3 patch set and installing the required components:

- [Install Oracle Enterprise Manager Console DB](#)
- [Apply Oracle Database Release 10.2.0.3 Patch Set](#)

Install Oracle Enterprise Manager Console DB

Before installing Oracle Database Vault, you should ensure that Oracle Enterprise Manager Console DB 10.2.0.3.0 is installed. Oracle Enterprise Manager Console DB is installed using the Oracle Universal Installer (OUI). The following steps summarize installing Oracle Enterprise Manager Console DB:

1. Run Oracle Universal Installer (OUI) and perform a custom installation to install Oracle Enterprise Manager Console DB 10.2.0.1.0. Add Oracle Enterprise Manager Console DB from the list of available product components.
2. Apply the Oracle Database release 10.2.0.3 patch set.

Note: You can configure the database to use Enterprise Manager Database Control by using Database Configuration Assistant (DBCA). However, configuring Enterprise Manager Database Control is not a prerequisite for installing Oracle Database Vault.

Apply Oracle Database Release 10.2.0.3 Patch Set

To install Oracle Database Vault, you need to upgrade the database to Oracle Database release 10.2.0.3. Oracle strongly recommends that you back up your database before performing any upgrade or installation.

See Also: *Oracle Database Backup and Recovery User's Guide* for information on database backups

This section covers the following topics:

Patch Set Overview

The patch set is not a complete software distribution. You must install it in an existing Oracle Database 10g release 2 (10.2.0.1 or 10.2.0.2) installation. You can apply the Oracle Database release 10.2.0.3 patch set to the following Oracle Database 10g release 2 installations:

- Oracle Database
- Oracle Real Application Clusters
- Oracle Database Client
- Oracle Database Companion CD
- Oracle Clusterware

Oracle Universal Installer Version Requirements

This patch set includes Oracle Universal Installer release 10.2.0.3, which is also installed when you install this patch set. This is to ensure that your Oracle home can be patched in the future. You should not use the Installer from the earlier maintenance release media or Oracle home.

Patch Set Documentation

There are two documents related to this release of the Oracle Database patch set:

- *Oracle Database Patch Set Notes, 10g Release 2 (10.2.0.3) Patch Set 2 for Microsoft Windows (32-Bit)*
- *Oracle Database List of Bugs Fixed, 10g Release 2 (10.2.0.3) Patch Set*

Both of these documents are included with the patch set. In addition, they are available on the Oracle*Metalink* Web site:

<http://metalink.oracle.com>

Prepare a Backup Strategy

Oracle strongly recommends that you back up your database before performing any upgrade or installation. The ultimate success of your upgrade depends heavily on the design and execution of an appropriate backup strategy. To develop a backup strategy, consider the following questions:

- How long can the production database remain inoperable before business consequences become intolerable?
- What backup strategy should be used to meet your availability requirements?
- Are backups archived in a safe, offsite location?
- How quickly can backups be restored (including backups in offsite storage)?
- Have recovery procedures been tested successfully?

Your backup strategy should answer all of these questions and include procedures for successfully backing up and recovering your database.

See Also: *Oracle Database Backup and Recovery User's Guide* for information on database backups

Verify That Oracle Clusterware Is Running (RAC Only)

Oracle Clusterware should be running for the Database Vault installer to find the existing Real Application Clusters (RAC) databases. If you have stopped Oracle Clusterware, then you should restart it before running Oracle Universal Installer. Use the following command to start Oracle Clusterware:

```
C:> CRS_HOME/bin/crsctl start crs
```

Note:

- You need to run the `crsctl start crs` command on all nodes of the cluster.
 - The `crsctl start crs` command also starts the database. You will need to shut down the database before running Oracle Universal Installer.
-
-

Stop Existing Oracle Processes

Stop all processes running in the Oracle home. You must complete this task to enable Oracle Universal Installer to relink certain executables and libraries. For RAC databases, you need to stop the processes on all nodes.

Stop the processes in the following order:

1. [Stop the Enterprise Manager Database Control Process](#)
2. [Stop the iSQL*Plus Process](#)
3. [Shut Down All Database Instances](#)

4. [Stop Existing Listeners](#)
5. [Stop Oracle Services](#)

Stop the Enterprise Manager Database Control Process

Stop the Enterprise Manager Database Control process, if it is running. Use the following command:

```
C:\> ORACLE_HOME\bin\emctl stop dbconsole
```

Stop the iSQL*Plus Process

Stop the iSQL*Plus process, using the following command:

```
C:\> ORACLE_HOME\bin\isqlplusctl stop
```

Shut Down All Database Instances

Shut down all database instances running from the Oracle home directory into which Oracle Database Vault is to be installed.

```
sqlplus SYS "AS SYSOPER"  
Enter password:  
SQL> shutdown immediate
```

Stop Existing Listeners

Oracle Universal Installer configures and starts a default Oracle Net listener using TCP/IP port 1521. However, if an existing Oracle Net listener process is using the same port or key value, then Oracle Universal Installer can only configure the new listener, it cannot start it. To ensure that the new listener process starts during the installation, you must shut down any existing listeners before starting Oracle Universal Installer.

Use the following command to stop the listener process:

```
C:\> ORACLE_HOME\bin\lsnrctl stop listenername
```

Stop Oracle Services

Use the following steps to stop Oracle Database services from the Control Panel:

1. Access your Windows Services dialog.

See Also: Your operating system documentation for instructions

2. Select OracleHOME_NAMETNSListener. Click **Stop** to stop this service. You need to perform this step only if you haven't shut down the listener process using the `lsnrctl` command.
3. Select OracleServiceSID and click **Stop**.

Note: If you are installing Database Vault for Oracle Real Application Clusters (RAC), then you need to shut down all Oracle processes on all cluster nodes. See [Appendix A, "How to Stop Processes in an Existing Oracle Real Application Clusters Database"](#) for more details.

Run Oracle Universal Installer to Install

You can use the graphical user interface (GUI) provided by Oracle Universal Installer to install Oracle Database. The following steps discuss installing Database Vault using Oracle Universal Installer:

1. Log on as a member of the Administrators group.
If you are installing on a Primary Domain Controller (PDC) or a Backup Domain Controller (BDC), log on as a member of the Domain Administrators group.
2. Insert Oracle Database Vault installation media and navigate to the database directory. Alternatively, navigate to the directory where you downloaded or copied the installation files.
Use the same installation media to install Oracle Database Vault on all supported Windows platforms.
3. Double-click `setup.exe` to start Oracle Universal Installer.
4. In the Specify Installation Details screen, you need to specify the path to the Oracle home that contains the existing Oracle Database. The **Destination Path** box lists the Oracle home paths of all Oracle Database release 2 (10.2.0.3) Enterprise Edition databases registered with the system.

Select the Oracle home corresponding to the database into which you want to install Oracle Database Vault.

Note:

- If an Oracle home does not have an Enterprise Edition of Oracle Database release 10.2.0.3 installed, then it is not displayed. You must ensure that the Oracle home has an Enterprise Edition of Oracle Database release 10.2.0.3 installed.
 - If an Oracle home does not have Oracle Enterprise Manager Console DB 10.2.0.3.0 installed, then it is not displayed. You must ensure that the Oracle home has Oracle Enterprise Manager Console DB 10.2.0.3.0 installed.
 - If an Oracle home contains an Automatic Storage Management (ASM) instance, then it is not displayed. You cannot install Oracle Database Vault into an Oracle home that also contains an ASM instance.
 - If an Oracle home already contains Oracle Database Vault, then it is not displayed. You cannot install Oracle Database Vault into an Oracle home more than once.
 - Oracle Clusterware should be running for the Database Vault installer to find the existing Real Application Clusters (RAC) databases. Ensure that Oracle Clusterware is running before installing Oracle Database Vault. You can use the `crsctl` command to start Oracle Clusterware.
-
-

5. Enter a user name for the Database Vault Owner account in the **Database Vault Owner** field. The user name can be a minimum of 2 and maximum of 30 characters long.
6. Enter a password for the Database Vault Owner account in the **Database Vault Owner Password** field. The password can be a minimum of 8 and a maximum of

30 characters. The password must include at least one alphabet, one digit, and one nonalphanumeric character (symbol). It cannot be the same as the account names for either the Database Vault owner or the Database Vault account manager. It cannot contain any consecutive repeating characters.

7. Reenter the password in the **Confirm Password** field.
8. Select **Create a Separate Account Manager** if you want to create a separate Account Manager to manage Oracle Database Vault accounts.
9. In the **Database Vault Account Manager** field, enter a user name for the Database Vault Account Manager if you have chosen to select the **Create a Separate Account Manager** check box. The user name can be a minimum of 2 and a maximum of 30 characters.
10. Enter a password for the Database Vault Account Manager account in the **Account Manager Password** field. The password can be a minimum of 8 and a maximum of 30 characters. The password must include at least one alphabet, one digit, and one nonalphanumeric character (symbol). It cannot be the same as the account names for either the Database Vault owner or the Database Vault account manager. It cannot contain any consecutive repeating characters.
11. Reenter the password in the **Confirm Password** field. Click **Next**.
12. The Select Existing Database screen is displayed. A list of all databases running from the selected Oracle home is displayed. Select the database into which you wish to install Oracle Database Vault.

Note:

- If the selected Oracle home contains more than one database, then Operating System (OS) authentication is turned off for all the databases in the Oracle home.
 - Oracle recommends that you install Oracle Database Vault into an Oracle home containing only a single database.
 - If a database is not listed, then check to make sure that you have followed the instructions under "[Check the Database Requirements](#)" on page 2-4.
-
-

13. Enter the existing SYS user password for the selected database in the **Existing Database SYS Password** field.
14. Reenter the SYS password in the **Confirm Password** field. Click **Next**.

Note: At this point, the database requirements are validated.

15. You are prompted to shut down all Oracle processes running from the Oracle home before proceeding. Shut down the Oracle processes, if you have not already done so.

See Also: "[Stop Existing Oracle Processes](#)" on page 2-6 for more information on stopping existing Oracle processes

16. Product-specific prerequisite checks are performed. Confirm that all tests have passed. Click **Next** to continue.

17. The Summary screen is displayed with the installation details. Verify the details and click **Install**.
18. The Installation screen is displayed. After the installation completes, the Database Vault Configuration Assistant (DVCA) is run automatically. DVCA helps configure the Database Vault installation.

Postinstallation Tasks

This section lists the tasks to perform after you have completed an upgrade of your database. The following topics are discussed:

- [Back Up the Database](#)
- [Change Passwords for Oracle-Supplied Accounts](#)
- [Enable or Disable Connections with the SYSDBA Privilege](#)
- [Start the Listener and Database on Other Nodes \(RAC Only\)](#)
- [Run DVCA to Set Instance Parameters and Lock Out SYSDBA Sessions \(RAC Only\)](#)
- [Restart Enterprise Manager Database Control](#)

Back Up the Database

Make sure you perform a full backup of the production database. See *Oracle Database Backup and Recovery User's Guide* for details on backing up a database.

Change Passwords for Oracle-Supplied Accounts

Oracle strongly recommends that you change the password for each account after installation. This enables you to effectively implement the strong security provided by Oracle Database Vault.

Note: If you are creating a database using Database Configuration Assistant, you can unlock accounts after the database is created by clicking **Password Management** before you exit from Database Configuration Assistant.

Using SQL*Plus to Unlock Accounts and Reset Passwords

To unlock and reset user account passwords using SQL*Plus:

1. Start SQL*Plus and log in using the Database Vault Account Manager account. If you did not create the Database Vault Account Manager account during installation, then you will need to log in using the Database Vault Owner account.
2. Enter a command similar to the following, where *account* is the user account that you want to unlock and *password* is the new password:

```
SQL> ALTER USER account [ IDENTIFIED BY password ] ACCOUNT UNLOCK;
```

In this example:

- The `ACCOUNT UNLOCK` clause unlocks the account.
- The `IDENTIFIED BY password` clause resets the password.

Note: If you unlock an account but do not reset the password, then the password remains expired. The first time someone connects as that user, they must change the user's password.

To permit unauthenticated access to your data through HTTP, unlock the `ANONYMOUS` user account.

See Also: *Oracle Database Administrator's Guide* for more information about:

- Unlocking and changing passwords after installation
- Oracle security procedures
- Best security practices

Enable or Disable Connections with the SYSDBA Privilege

In a default Database Vault installation, the operating system authentication to the database is disabled. In addition, connections to the database using the `SYSDBA` privilege (that is, those that use the `AS SYSDBA` clause) are disabled. This is a security feature and is implemented to prevent misuse of the `SYSDBA` privilege.

If a password file has been created using the `orapwd` utility with the `nosysdba` flag set to `y` (Yes) (the default action of a Database Vault installation), users will not be able to log in to an Oracle Database Vault instance using the `SYS` account or any account with `SYSDBA` privilege using the `AS SYSDBA` clause. You can reen able the ability to connect with the `SYSDBA` privilege by re-creating the password file with the `nosysdba` flag set to `n` (No). You might need to reen able the ability to connect with `SYSDBA` privileges, if certain products or utilities require it's use.

When you re-create the password file, any accounts other than `SYS` that were granted the `SYSDBA` or `SYSOPER` privileges will have those privileges removed. You will need to regrant the privileges for these accounts after you have re-created the password file.

Use the following syntax to run `orapwd`:

```
C:\> ORACLE_HOME\bin\orapwd file=filename password=password [entries=users]
force=y/n nosysdba=y/n
```

Where:

- `file`: Name of password file (mandatory)
- `password`: Password for `SYS` (mandatory). Enter at least six alphanumeric characters.
- `entries`: Maximum number of distinct DBA users
- `force`: Whether to overwrite the existing file (optional). Enter `y` (for yes) or `n` (for no)
- `nosysdba`: Whether to enable or disable the `SYS` logon (optional for Oracle Database Vault only). Enter `y` (for yes) or `n` (for no)

The default is `no`, so if you omit this flag, the password file will be created enabling `SYSDBA` access for Oracle Database Vault instances.

For example:

```
C:\> oracle\product\10.2.0\db_1\bin\orapwd
file=C:\oracle\product\10.2.0\db_1\dfs\orapwORCL password=5hjk99 force=y
```

nosysdba=n

Note: Do not insert spaces around the equal (=) character.

See Also: *Oracle Database Administrator's Guide* for more information on using the `orapwd` utility.

Start the Listener and Database on Other Nodes (RAC Only)

You need to start the listener and database on all RAC nodes other than the one on which the installation is performed. Use the following commands to start the listener and the database:

Note: You need to enable `SYSDBA` connections on all nodes before running these commands. See "[Enable or Disable Connections with the SYSDBA Privilege](#)" on page 2-11 for more information on enabling `SYSDBA` connections.

```
C:\> ORACLE_HOME\bin\lsnrctl start LISTENER_nodename
C:\> ORACLE_HOME\bin\svrctl start instance -d sid -i instance_name -c
"SYS/password AS SYSDBA"
```

Note: You must use the Server Control (`svrctl`) utility to start and stop Oracle Database Vault RAC instances. Do not use `SQL*Plus` to start and stop RAC instances. You need to enable `SYSDBA` connections before you can use the `svrctl` command.

Run DVCA to Set Instance Parameters and Lock Out SYSDBA Sessions (RAC Only)

After installing Database Vault for a Real Application Clusters (RAC) instance, you need to run Database Vault Configuration Assistant (DVCA) with the `-action optionrac` switch on all other RAC nodes. This sets instance parameters and disables `SYSDBA` operating system authentication.

Note:

- Before running DVCA on a remote node, you need to set the correct value for the ORACLE_SID variable in the `ORACLE_HOME\bin\dvca.bat` file on the remote node. The ORACLE_SID variable needs to be changed from the local node Oracle System Identifier (SID) to the remote node Oracle System Identifier (SID) on the remote node.
- Before running DVCA on a remote node, you need to correct the following Windows registry entry on the remote node:

```
HKEY_LOCAL_MACHINE\SOFTWARE\ORACLE\KEY_ORACLE_HOME_NAME\ORA_instance_name_PWFILE
```

The `instance_name` in the remote node registry should be the database instance name for the remote node, and not the database instance name for the local node.

The value for this key should be the complete path to the password file on the remote node. For example:

```
C:\ORACLE\PRODUCT\10.2.0\DB_1\dfs\orapwORCL2
```

You need to run this command on all RAC nodes other than the node on which the Database Vault installation is performed. This step is required to enable the enhanced security features provided by Oracle Database Vault.

Note: The listener and database instance should be running on the nodes on which you run DVCA.

Use the following syntax to run DVCA:

```
C:\> ORACLE_HOME\bin\dvca -action optionrac -racnode host_name -oh oracle_home
-jdbc_str jdbc_connection_string -sys_passwd sys_password [-logfile ./dvca.log]
[-silent] [-nodecrypt] [-lockout]
```

Where:

- `action`: The action to perform. `optionrac` performs the action of updating the instance parameters for the RAC instance and optionally disabling SYSDBA operating system access for the instance.
- `racnode`: The host name of the RAC node on which the action is being performed. Do not include the domain name with the host name.
- `oh`: The Oracle home for the RAC instance.
- `jdbc_str`: The JDBC connection string used to connect to the database. For example, "jdbc:oracle:oci:@orcl1".
- `sys_password`: The password for the SYS user.
- `logfile`: Optionally, specify a log file name and location. You can enter an absolute path or a path that is relative to the location of the `$ORACLE_HOME/bin` directory.
- `silent`: Required if you are not running DVCA in an xterm window.
- `nodecrypt`: Reads plaintext passwords as passed on the command line.

- `lockout`: Used to disable `SYSDBA` operating system authentication.

Note: You can reenable `SYSDBA` access by re-creating the password file with the `nosysdba` flag set to `n` (No). The `orapwd` utility enables you to do this.

Restart Enterprise Manager Database Control

Restart Enterprise Manager Database Control by using the following commands:

```
C:\> ORACLE_HOME\bin\emctl stop dbconsole
C:\> ORACLE_HOME\bin\emctl start dbconsole
```

Note: Run the above commands on all cluster nodes for a RAC database.

Removing Oracle Software

Use Oracle Universal Installer (OUI) to remove Oracle software from an Oracle home. The following list summarizes the steps involved:

1. Log on as a member of the Administrators group.
2. Shut down all processes running in the Oracle home.
3. Start Oracle Universal Installer from the **Start** menu, select **Programs**, then **ORACLE_HOME_NAME**, then **Oracle Installation Products**, then **Oracle Universal Installer**. The Welcome screen for Oracle Universal Installer appears.
4. In the Welcome screen, select **Deinstall Products**. The Inventory screen appears. This screen lists all the Oracle homes on the system.
5. Select the Oracle home and the products that you wish to remove. Click **Remove**.

See Also: Refer to the *Oracle Database Installation Guide* for details on removing Oracle software

Note: You cannot remove or uninstall the Database Vault option. However, you can disable Oracle Database Vault. Refer to *Oracle Database Vault Administrator's Guide* for more details.

You can also remove the entire Oracle home, as discussed earlier in this section.

Part II

Appendixes

Part II includes the appendixes. The contents of this part are:

- [Appendix A, "How to Stop Processes in an Existing Oracle Real Application Clusters Database"](#)
- [Appendix B, "Using Response Files"](#)
- [Appendix C, "Running DVCA After Creating a Database Vault Database"](#)
- [Appendix D, "Database Listener Security Recommendations"](#)
- [Appendix E, "Initialization Parameters"](#)
- [Appendix F, "Enabling Oracle Database Vault Administrator Accessibility"](#)

How to Stop Processes in an Existing Oracle Real Application Clusters Database

This appendix describes how to stop all processes in an Oracle Real Application Clusters (RAC) database, in preparation for installing Database Vault.

Note: Before you make any changes to the Oracle software, Oracle recommends that you create a backup of the Oracle Database installation.

Shut down the following Oracle Database services before modifying the Oracle Database software:

Note: You must perform these steps in the order listed.

1. Shut down any processes in the Oracle home on each node that can access a database. For example, you need to shut down Oracle Enterprise Manager Database Control.

```
C:\> ORACLE_HOME\bin\emctl stop dbconsole
```

Note: Before you shut down any processes that are monitored by Enterprise Manager Grid Control, set a blackout in Grid Control for the processes that you intend to shut down. This is necessary so that the availability records for these processes indicate that the shutdown was planned downtime, rather than an unplanned system outage.

2. Shut down all RAC instances on all nodes. To shut down all RAC instances for a database, enter the following command, where *db_name* is the name of the database:

```
C:\> ORACLE_HOME\bin\srvctl stop database -d db_name -c "SYS/password AS SYSDBA"
```

3. Stop all node applications on all nodes. To stop node applications running on a node, enter the following command, where *node* is the name of the node where the applications are running:

```
C:\> ORACLE_HOME\bin\srvctl stop nodeapps -n node -c "SYS/password AS SYSDBA"
```

-
4. Stop the `OracleServiceSID` service on all nodes. You can access the Services window from the Control Panel.

Using Response Files

This appendix describes how to install Oracle Database Vault using a response file. It includes the following topics:

- [How Response Files Work](#)
- [Installing Database Vault Using a Response File](#)
- [Troubleshooting Silent Mode Installation](#)

How Response Files Work

You can automate the installation and configuration of Oracle software by specifying a response file when you start Oracle Universal Installer. Oracle Universal Installer uses the values contained in the response file to provide answers to some or all of Oracle Universal Installer prompts.

Typically, Oracle Universal Installer runs in interactive mode, which means that it prompts you to provide information in graphical user interface (GUI) screens. When you use response files to provide this information, you run Oracle Universal Installer at a command prompt using the silent mode.

During a silent mode installation, Oracle Universal Installer does not display any screens. Instead, it displays progress information in the terminal that you used to start it.

You define the settings for a silent mode installation by entering values for the variables listed in the response file. For instance, to specify the Oracle home, you would supply the appropriate value for the `ORACLE_HOME` variable, as in the following example:

```
ORACLE_HOME = "C:\oracle\product\10.2.0\OraDBHome1"
```

Another way of specifying the response file's variable settings is to pass them as command line arguments when you run Oracle Universal Installer. For example:

```
SYSTEM_DRIVE:\setup.exe_location> setup -silent "ORACLE_HOME=C:\oracle\product\10.2.0\OraDBHome1" ...
```

This method is particularly useful if you do not want to embed sensitive information, such as passwords, in the response file. For example:

```
SYSTEM_DRIVE:\setup.exe_location> setup -silent "s_ownerPasswd=binks342" ...
```

Ensure that you enclose the variable and its setting in double quotation marks (" ").

See Also: *Oracle Universal Installer and OPatch User's Guide* for more information about response file formats

General Procedure for Using Response Files

The following are the general steps to install and configure Oracle products using Oracle Universal Installer in silent mode:

Note: You must complete all required preinstallation tasks on a system before running Oracle Universal Installer in silent mode.

1. Prepare a response file.
2. Run Oracle Universal Installer in silent mode.

Installing Database Vault Using a Response File

Use the following steps to install Database Vault using a response file:

1. [Prepare the Response File](#)
2. [Run Oracle Universal Installer Using the Response File](#)

Prepare the Response File

Oracle Database Vault comes with a response file template (`dv.rsp`) that you can edit to customize your installation. You can use this response file for silent mode installations.

The `dv.rsp` file is located in the `response` directory on the installation media. Use the following steps to copy and modify the response file:

1. Copy the response file from the `database\response` directory to a directory on your system.
2. Open the response file in a text editor.

The response file contains variables that store information required by Oracle Universal Installer. You need to set these variable values in the file. For example, you need to specify values for the Oracle home location, Database Vault owner name, and other such information required by Oracle Universal Installer.

The response file contains two parts. You should edit the variables only in the first part. The second part of the file contains preset variables, which must not be edited. This instruction is also provided in the response file.

Some of the variables are mandatory while others are optional. The mandatory variables must be supplied for a successful installation. Each variable is explained within the response file. Examples are also provided within the response file.

The following excerpt from the response file shows instructions related to setting the Oracle home variable:

```
#-----  
--  
#Name      : ORACLE_HOME  
#Datatype  : String  
#Description: Complete path of the existing 10.2.0.3.0 database Oracle  
#           Home into which Oracle Database Vault will be installed.  
#
```

```
#Requirement: 1) Must have Oracle Database Enterprise Edition release
#              10.2.0.3.0 installed.
#              2) Must have Oracle Enterprise Manager Console DB version
#              10.2.0.3.0 installed.
#              3) Cannot contain an Automatic Storage Management(ASM) instance.
#              4) Cannot contain Oracle Database Vault.
#
#Example: ORACLE_HOME = "C:\OHOME1"
#-----
--
ORACLE_HOME=<Value Required>
```

Lines starting with a pound sign (#) are comment entries. If you wish to omit an optional variable, you can comment it by adding a pound sign (#) at the beginning of the line. You cannot comment lines containing mandatory variables, like ORACLE_HOME.

Remember that you can specify sensitive information, such as passwords, at the command line rather than within the response file. ["How Response Files Work"](#) on page B-1 explains this method.

See Also: *Oracle Universal Installer and OPatch User's Guide* for detailed information on creating response files.

3. Follow the instructions in the file to edit it. Save and close the file.

Note: Oracle Universal Installer fails if you do not correctly configure the response file. Refer to the ["Troubleshooting Silent Mode Installation"](#) section on page B-4 for more information about troubleshooting a failed silent mode installation.

Run Oracle Universal Installer Using the Response File

Now, you are ready to run Oracle Universal Installer at the command line, specifying the response file you created, to perform the installation. The Oracle Universal Installer executable, `setup.exe`, provides several options. For help information on the full set of these options, run `setup.exe` with the `-help` option. For example:

```
SYSTEM_DRIVE:\setup.exe_location> setup -help
```

To run Oracle Universal using a response file:

1. Complete the preinstallation tasks listed in [Chapter 2, "Installing Oracle Database Vault as an Option"](#).

See Also: *Frequently Asked Questions in the Database Vault Release Notes* for a checklist of the preinstallation requirements

2. Log on as a member of the Administrators group.
3. To start Oracle Universal Installer in silent mode, enter a command similar to the following:

Note: Do not specify a relative path to the response file. If you specify a relative path, Oracle Universal Installer fails.

```
SYSTEM_DRIVE:\setup.exe_location> setup -silent -responseFile  
responsefilename
```

In this example:

- `-silent` indicates that you want to run Oracle Universal Installer in silent mode.
- `responsefilename` is the full path and file name of the installation response file that you configured.

Troubleshooting Silent Mode Installation

A silent installation fails in the following conditions:

- You do not specify a response file
- You specify an incorrect or incomplete response file
- Oracle Universal Installer encounters an error, such as insufficient disk space
- The Database Vault installation prerequisites have not been met

Oracle Universal Installer or configuration assistant validates the response file at run time. If the validation fails, the silent mode installation or configuration process ends. Oracle Universal Installer treats values for parameters that are of the wrong context, format, or type as if no value was specified in the file.

Running DVCA After Creating a Database Vault Database

You should run Database Vault Configuration Assistant (DVCA) after creating a new Oracle Database Vault database, if any of the following conditions is true:

- Database Vault is installed into an Oracle home that has more than one database. You need to run DVCA on the other databases in the Oracle home. This enables Database Vault security for those databases. The databases should meet the prerequisites for installing Oracle Database Vault, as discussed in "[Preinstallation and Installation Tasks](#)" on page 2-1.
- Database Configuration Assistant (DBCA) is used to create a new Database Vault database in an Oracle home that already has a Database Vault database. DVCA loads the Database Vault schema objects into the new database, creates the DV_OWNER and optional DV_ACCTMGR accounts, and deploys the Database Vault Administrator application for the database.

Use the following syntax to run the DVCA utility:

```
C:\> ORACLE_HOME\bin\dvca -action option [-racnode host_name] -oh oracle_home
-jdbc_str jdbc_connection_string -sys_passwd SYS_password -owner_account
DV_owner_account_name -owner_passwd DV_owner_account_password [-acctmgr_account
DV_account_manager_account_name] [-acctmgr_passwd DV_account_manager_password]
[-logfile ./dvca.log] [-silent] [-nodecrypt][-lockout] [-languages
{"en"}, {"de"}, {"es"}, {"fr"}, {"it"}, {"ja"}, {"ko"}, {"pt_BR"}, {"zh_CN"}, {"zh_TW"}]}
```

Where:

- **action**: The action to perform. **option** creates the Database Vault schema objects, creates the DV_OWNER account and the optional DV_ACCTMGR account, and deploys the Database Vault Administrator application.
- **racnode**: The host name of the Real Application Clusters (RAC) node on which the action is being performed. Do not include the domain name with the host name. Use this option if this is a RAC database.
- **oh**: The Oracle home for the database.
- **jdbc_str**: The JDBC connection string used to connect to the database. For example, `jdbc:oracle:oci:@orcl1`, where `orcl1` is the net service name in the `tnsnames.ora` file (`$ORACLE_HOME/network/admin/tnsnames.ora`).
- **sys_passwd**: Password for user SYS
- **owner_account**: Oracle Database Vault Owner account name
- **owner_passwd**: Oracle Database Vault owner account password

-
- `acctmgr_account`: (Optional) Oracle Database Vault Account Manager user
 - `acctmgr_passwd`: Oracle Database Vault Account Manager password (if a user name has been specified)
 - `logfile`: Optionally, specify a log file name and location. You can enter an absolute path or a path that is relative to the location of the `$ORACLE_HOME/bin` directory
 - `silent`: Required if you are not running DVCA in an xterm window
 - `nodecrypt`: Reads plaintext passwords as passed on the command line. You must use this option if you are passing plaintext passwords to the command.
 - `lockout`: Disables SYSDBA operating system authentication
 - `languages`: Declares the language content to load, defaults to "en" (English). You can specify multiple languages. Include each language in quotation marks with commas separating different languages. Enclose the list of languages in braces. For example, `-languages {"en", "fr", "ja"}`.

The following lists the language key:

- `de`: German
- `en`: English
- `es`: Spanish
- `fr`: French
- `it`: Italian
- `ja`: Japanese
- `ko`: Korean
- `pt_BR`: Brazilian Portuguese
- `zh_CN`: Simplified Chinese
- `zh_TW`: Traditional Chinese

Note:

- If the Oracle system identifier (SID) of the database is more than 8 characters, then you would need to update the Net service name in the `tnsnames.ora` file before running DVCA. See *Oracle Database Vault Release Notes* for more information.
 - DVCA should also be run before and after installing database options like Spatial, Java, and Intermedia. See *Oracle Database Vault Administrator's Guide* for more details.
-
-

If you have used the `lockout` option with the `dvca` command, then to successfully lockout SYSDBA connections, you also need to add the following values to your Microsoft Windows registry under `HKEY_LOCAL_MACHINE\SOFTWARE\ORACLE\KEY_ORACLE_HOME_NAME`:

Table C-1 Registry Values to Be Added

Name	Type	Data
ORA_SID_PWFIL	REG_SZ	<i>Path_to_the_password_file</i>
For example,		For example,
ORA_ORCL_PWFIL		C:\ORACLE\PRODUCT\10.2.0\DB_1\dfs\ orapwORCL

Note:

- For a Real Application Clusters (RAC) database, replace *SID* with *instance_name*, which is the *SID* combined with the *instance_number*.
 - For a RAC database, you need to add the registry values for all cluster nodes.
-

For a RAC database, you also need to run the `dvca -action optionrac` command on all nodes other than the node on which the installation is performed. Refer to "[Run DVCA to Set Instance Parameters and Lock Out SYSDBA Sessions \(RAC Only\)](#)" on page 2-12 for details.



Database Listener Security Recommendations

This appendix lists the security recommendations for protecting the database listener.

Security Checklist for the Database Listener

The following configuration guidelines help enhance the security for your database listener:

- The database listener configuration file, `listener.ora`, and the supporting OracleNet configuration file, `tnsnames.ora`, should have the `ADMIN_RESTRICTIONS_LISTENER_SID=ON` protection enabled.
- The database listener configuration file, `listener.ora`, and the supporting OracleNet configuration file, `tnsnames.ora`, should have the `PLSExtProc` listener disabled.
- The listener should be configured to listen on a non-standard port. This means that the default port (1521) should be changed.
- The listener should be password protected or leverage operating system (OS) authentication based on the organizational security policy.
- The listener should use a unique name, which should be different from the default name.

- The `listener.ora` file should have the following parameter set:

```
INBOUND_CONNECT_TIMEOUT_ListenerName = 10
```

- The `sqlnet.ora` file should have the following parameters set:

```
SQLNET.INBOUND_CONNECT_TIMEOUT = 12  
SQLNET.EXPIRE_TIME = 10
```

- The listener should have logging enabled as follows:

```
LOGGING_LISTENER = ON  
LOG_STATUS = ON  
LOG_DIRECTORY_ListenerName = Directory_owned_by_Administrator  
LOG_FILE_ListenerName = File_owned_by_Administrator
```

Note: Only the Administrators group should have permissions over the LOG_DIRECTORY.

Only the Administrators group should have read and write permissions over the LOG_FILE.

- The listener should have tracing enabled as follows:

```
TRACE_DIRECTORY_ListenerName = Directory_owned_by_Oracle_account
TRACE_FILE_ListenerName = File_owned_by_Oracle_account
TRACE_LEVEL = user
TRACE_FILELEN_ListenerName = 512
TRACE_FILENO_ListenerName = 1000
TRACE_TIMESTAMP_ListenerName = dd-mon-yyyy hh:mi:ss:mi
```

Note: Only the Administrators group should have read and write permissions over the TRACE_DIRECTORY.

Only the Administrators group should have read and write permissions over the TRACE_FILE.

Initialization Parameters

When you install Oracle Database Vault, the security specific database initialization parameters are initialized with default values. The following list shows the default values for these security specific initialization parameters:

```
REMOTE_LOGIN_PASSWORDFILE = default, EXCLUSIVE
AUDIT_SYS_OPERATIONS = TRUE
REMOTE_OS_AUTHENT = FALSE
REMOTE_OS_ROLES = FALSE
OS_ROLES = FALSE
OS_AUTHENT_PREFIX = ''
SQL92_SECURITY = TRUE
O7_DICTIONARY_ACCESSIBILITY = FALSE
```

Enabling Oracle Database Vault Administrator Accessibility

As part of the effort to make Oracle products, services, and supporting documentation accessible and usable to the disabled community, Oracle Database Vault Administrator offers several features that make management data available to users of assistive technology. To enable these features and provide for full accessibility, you must modify two configuration settings, which are described in the following sections:

- [Enabling Oracle Database Vault Administrator Accessibility Mode](#)
- [Providing Textual Descriptions of Database Vault Administrator Charts](#)

Enabling Oracle Database Vault Administrator Accessibility Mode

Oracle Database Vault Administrator takes advantage of user interface development technologies that improve the responsiveness of some user operations. For example, when you navigate to a new record set in a table, Oracle Database Vault Administrator does not redisplay the entire HTML page. However, this performance-improving technology is generally not supported by screen readers. To disable this feature, and as a result, make the Database Vault Administrator HTML pages more accessible for disabled users, use the following procedure.

To enable the display of an entire HTML page:

1. Locate the `uix-config.xml` configuration file.

To locate the `uix-config.xml` file in an Oracle Database 10g installation, change directory to the following location in the Oracle home:

```
ORACLE_HOME\dv\jlib\dva_webapp\dva_webapp\WEB-INF
```

2. Open the `uix-config.xml` file using a text editor and locate the following entry:

```
<!-- An alternate configuration that disables accessibility features -->
<default-configuration>
  <accessibility-mode>inaccessible</accessibility-mode>
</default-configuration>
```

3. Change the value of the `accessibility-mode` property from `inaccessible` to `accessible`.
4. Save and close the `uix-config.xml` file.
5. Restart Database Vault Administrator.

See Also: For more information on starting Oracle Database Vault Administrator, refer to *Oracle Database Vault Administrator's Guide*.

Providing Textual Descriptions of Database Vault Administrator Charts

In the Monitor page of the Database Vault Administrator, a chart is used to display security policy data. However, charts do not convey information in a manner that can be read by a screen reader. To remedy this problem, you can configure Database Vault Administrator to provide a complete textual representation of each chart. By default, support for the textual representation of charts is disabled. When textual description for charts is enabled, Database Vault Administrator displays a textual representation of the chart data.

To enable the textual representation of charts:

1. Locate the `web.xml` configuration file.

To locate the `web.xml` file in a Oracle Database 10g installation, change directory to the following location in the Oracle home:

```
ORACLE_HOME\dv\jlib\dva_webapp\dva_webapp\WEB-INF
```

2. Open the `web.xml` file with your favorite text editor and locate the following six lines of the file:

```
<!-- Uncomment this to enable textual chart descriptions
<context-param>
<param-name>enableChartDescription</param-name>
<param-value>>true</param-value>
</context-param>
-->
```

3. Remove comments from this section by deleting the first line and the last line of this section so that the section consists of only these four lines:

```
<context-param>
<param-name>enableChartDescription</param-name>
<param-value>>true</param-value>
</context-param>
```

4. Save and exit the `web.xml` file.
5. Restart Database Vault Administrator.

See Also: For more information on starting Oracle Database Vault Administrator, refer to *Oracle Database Vault Administrator's Guide*.

Numerics

10.2.0.3 patch set, 2-5

A

accessibility features, F-1

Account Manager, 2-9

accounts

 Database Vault Account Manager, 1-2

 Database Vault Owner, 1-1

 unauthenticated access to, 2-11

Administrators group, 2-8

ANONYMOUS user

 unauthenticated account access with, 2-11

applying 10.2.0.3 patch set, 2-5

assistive technology, F-1

audit policy, 1-2

B

backups

 after upgrading, 2-10

 importance, 2-6

 preparing a strategy, 2-6

C

certification, hardware and software, 1-2

change passwords

 for oracle-supplied accounts, 2-10

checking

 database requirements, 2-4

 hardware requirements, 2-2

 software requirements, operating system requirements, 2-3

compilers

 supported, 2-3

D

database (RAC)

 starting, 2-12

 stopping processes, A-1

database requirements, 2-4

Database Vault

 accounts, 1-1

 audit policy, 1-2

 initialization parameters, 1-2

Database Vault Account Manager account, 1-2

 password, 1-2

 user name, 1-2

Database Vault Configuration Assistant, 2-12

Database Vault Owner, 2-8

Database Vault Owner account, 1-1

 password, 1-1

 user name, 1-1

disk space

 checking, 2-2

 requirements, 2-2

DV_ACCTMGR role, 1-2

DV_OWNER role, 1-1

DVCA

See Database Vault Configuration Assistant

dvca command, 2-12, 2-13, C-1

E

Enterprise Manager Console DB

 installing, 2-5

environment variables

 TEMP and TMP

 hardware requirements, 2-2

errors

 silent mode, B-4

F

files

 response files, B-2

H

hardware and software certifications, 1-2

hardware certification, 1-2

hardware requirements, 2-2

I

initialization parameters, 1-2, E-1

installation

 considerations, 1-2

 errors

- silent mode, B-4
- response files, B-1, B-2
 - preparing, B-2
 - silent mode, B-4
 - templates, B-2
- silent mode, B-4
 - error handling, B-4
- installing
 - Enterprise Manager Console DB, 2-5
 - Oracle Universal Installer, using, 2-8

L

- listener, 2-4
 - security checklist, D-1
 - stopping existing listener process, 2-7
- listener (RAC)
 - starting, 2-12
- logging on
 - SYSDBA privilege connections, enabling, 2-11

M

- memory requirements, 2-2
- monitoring
 - accessibility features, enabling, F-2
 - textual representation in charts, enabling, F-2
- multiple Oracle homes, 1-3

N

- network protocols, supported, 2-4

O

- operating system requirements, 2-3
- operating systems, supported, 2-3
- Oracle Clusterware
 - starting, 2-6
- Oracle Database Client
 - requirements, 2-4
- Oracle Database Vault
 - audit policy, 1-2
 - initialization parameters, 1-2, E-1
- Oracle Database Vault Administrator
 - accessibility features, enabling, F-1
- Oracle homes, multiple, 1-3
- Oracle Net
 - stopping existing listener, 2-7
- Oracle services
 - stopping, 2-7
- Oracle Universal Installer, 2-5, 2-7, 2-8, 2-14
 - response files, B-1
- oracle-supplied accounts
 - change passwords, 2-10
- orapwd utility, 2-11
- OUI, 2-5

P

- password file, 2-4

- passwords
 - Database Vault Account Manager, 1-2
 - Database Vault Owner, 1-1
 - password files, 2-11
 - resetting
 - with SQL*Plus, 2-10
 - specifying for response files, B-1
 - unlocking
 - with SQL*Plus, 2-10
 - See also* security
- patch set
 - applying, 2-5
 - documentation, 2-5
- privileges
 - SYSDBA, enabling or disabling connection, 2-11
- process
 - stopping existing, 2-6
 - stopping existing listener process, 2-7

R

- RAM requirements, 2-2
- Real Application Clusters
 - Instance Parameters, setting, 2-12
 - SYSDBA sessions, locking, 2-12
- REMOTE_LOGIN_PASSWORDFILE parameter, 2-4
- removing, Oracle Software, 2-14
- requirements
 - database, 2-4
 - hardware, 2-2
 - listener, 2-4
 - Oracle Database 10.2.0.3 patch set, 2-5
 - Oracle Database Client, 2-4
 - Oracle Enterprise Manager Console DB
 - 10.2.0.3, 2-4
 - password file, 2-4
 - software, operating system, 2-3
- response files
 - about, B-1
 - general procedure, B-2
 - passing values at command line, B-1
 - passwords, B-1
 - security, B-1
 - specifying with Oracle Universal Installer, B-3
 - See also* silent mode, B-1
- response files installation
 - about, B-1
- roles
 - DV_ACCTMGR, 1-2
 - DV_OWNER, 1-1

S

- screen
 - Specify Installation Details, 2-8
- security
 - See also* passwords
- security checklist
 - database listener, D-1
- services

- stopping, 2-7
- setup.exe file, 2-8
- silent mode installation, B-4
- software and hardware certifications, 1-2
- software certification, 1-2
- software requirements, operating system requirements, 2-3
- specifying installation details, 2-8
- srvctl command, 2-12
- stopping
 - Oracle processes, 2-6
- stopping Oracle services, 2-7
- stopping RAC processes, A-1
- SYSDBA privilege
 - enabling or disabling connections with, 2-11
- system architecture, supported, 2-3

T

- TEMP environment variable, hardware requirements, 2-2
- temporary directory, 2-2
- temporary disk space
 - checking, 2-2
 - freeing, 2-2
 - requirements, 2-2
- tmp directory
 - checking space in, 2-2
 - freeing space in, 2-2
- TMP environment variable
 - hardware requirements, 2-2

U

- upgrading
 - after upgrading, 2-10
 - backup strategy, 2-6
 - post upgrade actions, 2-10
- user names
 - Database Vault Account Manager, 1-2
 - Database Vault Owner, 1-1
- users
 - Database Vault Account Manager, 1-2
 - Database Vault Owner, 1-1

W

- Windows
 - Administrators group, 2-8
 - compilers, supported, 2-3
 - network protocol, supported, 2-4
 - operating systems, supported, 2-3
 - system architecture, supported, 2-3

